

Depreciation Menu

<div style="background-color: #333; color: white; padding: 5px; border-radius: 5px; text-align: center;"> BASIS value 10,000.00 </div>	<div style="background-color: #c00; color: white; padding: 5px; border-radius: 5px; margin-bottom: 5px;">SL</div>	<div style="background-color: #c00; color: white; padding: 5px; border-radius: 5px; margin-bottom: 5px;">SOYD</div>
<div style="background-color: #333; color: white; padding: 5px; border-radius: 5px; text-align: center;"> SALVAGE value 500.00 </div>	<div style="background-color: #c00; color: white; padding: 5px; border-radius: 5px; margin-bottom: 5px;">DB</div>	<div style="background-color: #c00; color: white; padding: 5px; border-radius: 5px; margin-bottom: 5px;">ACRS</div>
<div style="display: flex; justify-content: space-between;"> <div style="background-color: #333; color: white; padding: 5px; border-radius: 5px; width: 45%; text-align: center;"> Life (yrs) 5 </div> <div style="background-color: #333; color: white; padding: 5px; border-radius: 5px; width: 45%; text-align: center;"> DB Fact% 200.00 </div> </div>	<div style="background-color: #ffc000; padding: 5px; border-radius: 5px; margin-top: 10px; width: 100%;">Table</div>	

This menu allows depreciation calculations for the common methods:

- Declining balance (DB).
- Sum-of-the-years'-digits (SOYD).
- Straight line (SL)
- Accelerated Cost Recovery System (ACRS)

Depreciation Menu Actions	
[BASIS]	Stores the depreciable cost of the asset at acquisition.
[SALVAGE]	Stores the salvage value of the asset at the end of its useful life.
[Life]	Stores the expected useful life of the asset in years.
[DB Fact%]	Stores the declining-balance factor as a % of the straight-line rate.
[DB]	Calculates the declining-balance depreciation for the year.
[SOYD]	Calculates the sum-of-years-digits depreciation for the year.
[SL]	Calculates the straight-line depreciation for the.
[ACRS]	Calculates the ACRS deduction based on Basis and Acrs% values.
[Table]	Opens a view with depreciation schedule for all years.

To calculate the depreciation for a given year, type the year (1, 2, 3, etc.) in the calculator and touch the **SL**, **SOYD** or **DB** buttons. The remaining depreciable value (RDV) is also calculated and placed in the 'Y' display register.

To calculate the Accelerated Cost Recovery Deduction, type the ACRS percentage in the calculator and touch the **ACRS** button.

Example: Depreciation Methods

An asset purchased in \$10,000, is depreciated over 5 years. Its salvage value is \$500. Find the depreciation and remaining value for the first 2 years using all three depreciation methods (in the DB method use a declining factor of 200).

Solution:

Keystroke	Description
10000 [Basis]	Input the original asset depreciable value.
500 [Salvage]	Input the salvage value of the asset at the end of useful life.
5 [Life]	Stores the useful life of the asset.
200 [Fact%]	Stores the Declining Balance factor.
1 [DB]	Calculates DB for year #1: DEP = 4,000.00; RDV = 5,500.00
1 [SOYD]	Calculates SOYD for year #1: DEP = 3,166.67; RDV = 6,333.33
1 [SL]	Calculate the SL for year #1: DEP = 1,900.00; RDV = 7,600.00
2 [DB]	Calculate the DB for year #2: DEP = 2,400.00; RDV = 3,100.00
2 [SOYD]	Calculate the SOYD for year #2: DEP = 2,533.33; RDV = 3,800.00
2 [SL]	Calculate the SL for year #2: DEP = 1,900.00; RDV = 5,700.00

To visualize the complete depreciation schedule from the first to the last period, touch the [**Table**] button. Additionally, in the table view you can touch the [**Copy**] button to copy the complete schedule as text and paste it in any other application for further use (for example in a email message).

'SL' Depreciation Schedule		
Year: 0		
DPN		0.00
RDV		9,500.00
RBV		10,000.00
Year: 1		
DPN		1,900.00
RDV		7,600.00
RBV		8,100.00
Year: 2		
DPN		1,900.00
RDV		5,700.00
RBV		6,200.00
Year: 3		
DPN		1,900.00
RDV		3,800.00
RBV		4,300.00
Year: 4		
DPN		1,900.00
RDV		1,900.00
RBV		2,400.00
Year: 5		
DPN		1,900.00
RDV		0.00
RBV		500.00

'SOYD' Depreciation Schedule		
Year: 0		
DPN		0.00
RDV		9,500.00
RBV		10,000.00
Year: 1		
DPN		3,166.67
RDV		6,333.33
RBV		6,833.33
Year: 2		
DPN		2,533.33
RDV		3,800.00
RBV		4,300.00
Year: 3		
DPN		1,900.00
RDV		1,900.00
RBV		2,400.00
Year: 4		
DPN		1,266.67
RDV		633.33
RBV		1,133.33
Year: 5		
DPN		633.33
RDV		0.00
RBV		500.00

'DB' Depreciation Schedule		
Year: 0		
DPN		0.00
RDV		9,500.00
RBV		10,000.00
Year: 1		
DPN		4,000.00
RDV		5,500.00
RBV		6,000.00
Year: 2		
DPN		2,400.00
RDV		3,100.00
RBV		3,600.00
Year: 3		
DPN		1,440.00
RDV		1,660.00
RBV		2,160.00
Year: 4		
DPN		864.00
RDV		796.00
RBV		1,296.00
Year: 5		
DPN		518.40
RDV		277.60
RBV		777.60

SL
SOYD
DB

Copy
Done

SL
SOYD
DB

Copy
Done

SL
SOYD
DB

Copy
Done